

# Email Setup for Windows Mail (Vista)


1. Click the **Start** button. Click **Windows Mail**.



2. Click the **Tools** menu, and then click **Accounts**.



3. Click the **Add** button.



4. Click the **E-mail Account** option. Click **Next**.



5. Enter your name in the **Display name** box. Click **Next**.



6. Enter your GLBB email address in the **E-mail address** box. Click **Next**.
7. In the **Set up e-mail servers** window make these settings. Click **Next**.

<b>Incoming e-mail server type</b>	POP3 or IMAP
<b>Incoming mail (POP3 or IMAP) server</b>	(POP) pop.glbb.jp (IMAP)imap.glbb.jp
<b>Outgoing e-mail server (SMTP) server</b>	smtp.glbb.jp
<b>Outgoing server requires authentication</b>	Check the box

8. In the **Internet Mail Logon** window make these settings. Click **Next**.


<b>E-mail username</b>	Your GLBB Email Username. Enter as is on the Information sheet
<b>Password</b>	Your GLBB Email Password. Enter as is on the Information sheet
<b>Remember password</b>	Check this if you don't want to type your password every time you check for new email.

9. Check the **Do not download my e-mail at this time** box. Click the **Finish** button.
10. The **Internet Accounts** window will appear showing the new account you have made. Highlight that account and then click the **Properties** button.



11. Click the **Servers** tab. Make these settings.

<b>My incoming mail server is ...</b>	POP3 or IMAP
<b>Incoming mail (POP3)</b>	pop.glbb.jp
<b>Incoming mail (IMAP)</b>	imap.glbb.jp
<b>Outgoing mail (SMTP)</b>	smtp.glbb.jp
<b>E-mail username</b>	Your GLBB Email User ID
<b>Password</b>	Your GLBB Email Password
<b>Remember password</b>	Check the box if you don't want to have to type your password every time you download your email.
<b>Log on using Secure Password Authentication</b>	Do not check this box.
<b>My server requires authentication</b>	Check this box.



12. Click the **Settings** button.

13. Click the **Use the same settings as my incoming mail server** box.


Click the **OK** button.



14. Click the **Advanced** tab. Make these settings.

<b>Incoming mail (POP)</b>	110
<b>Incoming mail (IMAP)</b>	143
<b>Outgoing mail (SMTP)</b>	587

15. Confirm that the port numbers are still in their respective boxes. Click the **Apply** button. Click the **OK** button.



16. The **Internet Accounts** window will appear. Click the **Close** button.

17. If your computer is connected to the Internet, click the **Send/Receive** button to download your email.